



---

## Rockland Technical Note 057

### **– Rockland API– Customer Facing Document**

---

JP Juteau

2022-10-12

Rockland Scientific International Inc.

520 Dupplin Rd

Victoria, BC, CANADA, V8Z 1C1

[www.rocklandscientific.com](http://www.rocklandscientific.com)

---

## Copyright Notice

---

Copyright © 2022 by Rockland Scientific International, Inc. All rights reserved.

This publication is protected by copyright, and permission must be obtained from the publisher prior to any prohibited reproduction, storage in a retrieval system, or transmission in any form or by any means, electronic, mechanical, photocopying, recording, or likewise.

info@rocklandscientific.com  
tel: +1 250 370 1688

---

## Version History

---

Date	Description
2022-05-20	Initial creation
2022-10-12	Updating information to new API framework

## Contents

1	Introduction . . . . .	2
1.1	Workflow . . . . .	3
2	Logging into the Rockland API . . . . .	4
3	Create Project . . . . .	5
4	Upload data . . . . .	6
5	Get Data . . . . .	8
A	Data Types . . . . .	11

## List of Tables

1	Kinematics Sensor Data Types . . . . .	11
2	Instrument Meta Data Types . . . . .	11
3	Instrument Speed Data Types . . . . .	11
4	CT Sensor Data Types . . . . .	12
5	Chlorophyll, Turbidity and Dissolved Oxygen Sensors Data Types. . . . .	12
6	Microstructure Sensor Data Types . . . . .	12
7	Shear Quality Control Data Types . . . . .	12
8	Spectral Data Types . . . . .	13
9	Computed Value Data Types . . . . .	13

# 1 Introduction

This document provides a short guide to interacting with the Rockland API for the purpose of decoding Rockland q-files and extracting your decoded data from our database. To do so, the document will describe:

1. Log in and authentication
2. Uploading Slocum \*.mri files
3. Downloading data types.

The Rockland API is accessible at the following URL: <https://rocklandapi.azurewebsites.net>

In order to connect to the Rockland API, you will need to create an account in the [Rockland Online Portal](#). An email should have been sent (perhaps received in your junk folder) with a link to login and create an account with its credentials. Those same credentials (email address and password) will be used to connect to the Rockland API.

If you experience any issues setting up your user account in the Rockland Online Portal, please contact [zissou@rocklandscientific.com](mailto:zissou@rocklandscientific.com).



To facilitate the integration, the text below provides snippets of Python code to perform the API queries. This code was auto-generated and should be tested before being used.

## 1.1 Workflow

The expected workflow for interacting with the API is described below:

1. Confirm your credentials are working
2. Create a Project to store your data
3. Data files are uploaded to the Project as "Profiles"
4. The decoded data from Profiles can be queried from the API

### Project Creation

A project must be created to hold your microstructure data. The Project requires a name and an instrument serial number to be created. If the project is successfully created, a token will be returned to uniquely identify the project for further requests.

### Uploading data

Once a project has been created, your q-files can be uploaded to the project. This requires uploading the \*.mri or \*.q file to create a "Profile".

During the process, the data will be parsed from the file and stored in the database. The data will be accessible using the profile identification token returned by the endpoint.

### Retrieving data

Finally, to extract data from the database, the easiest method is to query the data using profiles and data identifiers. Each profile has a unique token and each data types (e.g.  $\epsilon_1$ ,  $\Phi_{\nabla u_1}(f)$ , etc.) has a unique hexadecimal identifier.

## 2 Logging into the Rockland API

To perform most requests in the Rockland API, an authentication token is required which identifies you as a user. The first step to interact and query the API is to log-in *i.e.* get an authentication token. To do so, you will need:

- Your Rockland Online Portal username (email address)
- Your Rockland Online Portal password (created when first logging into the Rockland Online Portal)
- A Source Token (c6X2ADq9YqA3Hh5)
- Your organization name as presented in the Rockland Online Portal (Oregon State University)

The code below provides an example of such a query using Python's `http.client` package.

```
import http.client
import json

conn = http.client.HTTPSConnection("rocklandapi.azurewebsites.net")

payload = json.dumps({
    "username": "your_username@mail.com",
    "password": "your_password",
    "sourceToken": "c6X2ADq9YqA3Hh5",
    "OrganizationName": "Oregon_State_University"
})
headers = {
    'Content-Type': 'application/json'
}
conn.request("POST", "/api/Auth/Login", payload, headers)
result = conn.getresponse()
```

The expected response includes an authentication token and a tokenExpiry. The token includes information about your user identity and your organization. For security purposes, the token is set to expire an hour after the log in (note that times are set in UTC).

```
"message": "",
"body": {
    "token": "eyJhbGciOiJIUzI1BgLSnT5aCI5IstdGFK8.eyJzbnVzZXNjb3VfQWlyZHJvcCI5InBOIjoimMmQ5ODE2YmY0OTkxNDUxOWEyMzE3M2E0ZjlmYmRhODciLCJleHAiOjE2NTk3MTU3MTMsImIzcyI6Imh0dHA6Ly9yb2NrbGFuZGFwaS5henVvZXdlYnNpB07EQ0G2B1XVTWxnaweb7Ctc8InF1ZCI6ImFhNTQyZmZjLWU4NjItNDEwNy05NzY4YmIwN2M5YiJ9bFwE7QATquWW14ID7MA35iPhp2a5sSfozeLfMHYR4-I",
    "tokenExpiry": "2022-08-05T16:08:33.2058928Z",
    "message": ""
}
```

### 3 Create Project

The Project/Create endpoint will create a new empty project. To create the project you will need to provide the following:

- Your Rockland authentication token, outputted by the Login endpoint
- A name for the project
- An optional description for the project
- The serial number of the instrument used to collect data for the project

The code below provides an example of such a query using Python's `http.client` package. The payload and token variables need to be edited.

```
import http.client
import json

conn = http.client.HTTPSConnection("rocklandapi.azurewebsites.net")

payload = json.dumps({
    "Name": "Project_Name",
    "Description": "Project_Description",
    "DataType": "RDL_isdp",
    "Instruments": [
        {
            "InstrumentSN": "SN123"
        }
    ]
})

token = "eyJhbGciOiJIUzI1BgLSnPnT5aCI5IstDGFK8.eyJzbX8GW86iJaaXNzb3VfQWlyZHJvcCI5InB0IjoIImMmQ5ODE2YmY0OTkxNDUxOWEyMzE3M2E0ZjlmYmRhODciLCJleHAiOiJ2NTk3MTU3MTMsImIzcyI6Imh0dHA6Ly9yb2NrbGFuZGFwaS5henVyZXdlYnNpB07EQ0G2B1XVTWxnaweb7Ctc8InF1ZCI6ImFhNTQyZmZjLWU4NjltNDEwNy05NzY4YmlwN2M5YiJ9bFwE7QATquWW14ID7MA35iPhp2a5sSfozeLfMHYR4-I"

headers = {
    'Authorization': 'Bearer ' + token,
    'Content-Type': 'application/json'
}

conn.request("POST", "/api/Project/Create", payload, headers)
result = conn.getresponse()
```

The expected response includes a project token that can be used to add profiles to the project.

```
"message": "",
"body": "f8b45014-1606-4fbe-94f7-bdd9b24c802e"
```

## 4 Upload data

Uploading data files to the Rockland database consists in creating new profiles in the project. This is done using the Profile/New endpoint.

To call the endpoint you will require the following:

- Your Rockland authentication token (JWT) outputted by the Login endpoint
- A Project token from the Project/Create endpoint
- A data file (.mri or \*.q)

The code below provides an example of such a query using Python's `http.client` package. The `filePath`, `projectToken` and `token` variables need to be edited.

```
import http.client
from codecs import encode

filePath = 'path/to/file.mri'

projectToken = "f8b45014-1606-4fbe-94f7-bdd9b24c802e"

token = "eyJhbGciOiJIUzI1BgLSnPnT5aCI5IstDGFK8.eyJzbX8GW86iJaaXNzb3VfQWlyZHJvcCIlnB0ljoIMmQ5ODE2YmY0OTkxNDUxOWEyMzE3M2E0ZjlmYmRhODciLCJleHAiOiJlE2NTk3MTU3MTMslmIzcyI6Imh0dHA6Ly9yb2NrbGFuZGFwaS5henVyZXdlYnNpB07EQ0G2B1XVTWxnaweb7Ctc8lnF1ZCI6ImFhNTQyZmZjLWU4NjltNDEwNy05NzY4YmlwN2M5YiJ9bFwE7QATquWW14ID7MA35iPhp2a5sSfozeLfMHyR4-I"

fileType = "RDL_isdp"

conn = http.client.HTTPSConnection("rocklandapi.azurewebsites.net")

dataList = []
boundary = 'wL36Yn8afVp8Ag7AmP8qZ0SA4n1v9T'
dataList.append(encode('--' + boundary))

dataList.append(encode(
    'Content-Disposition: form-data; name=; filename=file'))
dataList.append(encode('Content-Type: application/octet-stream'))
dataList.append(encode(''))
with open(filePath, 'rb') as f:
    dataList.append(f.read())

dataList.append(encode('--' + boundary))

dataList.append(encode(
```



```
'Content-Disposition': 'form-data; name=ProjectToken;'))
dataList.append(encode('Content-Type: text/plain'))
dataList.append(encode(''))
dataList.append(encode(projectToken))

dataList.append(encode('--' + boundary))

dataList.append(encode(
    'Content-Disposition: form-data; name=FileType;'))
dataList.append(encode('Content-Type: text/plain'))
dataList.append(encode(''))
dataList.append(encode(fileType))

dataList.append(encode('--'+boundary+'--'))
dataList.append(encode(''))
body = b'\r\n'.join(dataList)
payload = body
headers = {
    'Authorization': 'Bearer ' + token,
    'Content-type': 'multipart/form-data; boundary={}'.format(boundary)
}
conn.request("POST", "/api/Profile/New", payload, headers)
result = conn.getresponse()
```

If the profile creation was successful, the endpoint will return a success message as follows:

```
"message": "Success",
"body": null
```

## 5 Get Data

To get your data from one or multiple profiles, you can call the Data/Get endpoint.

To call the endpoints you will require the following:

- Your Rockland authentication token (JWT) outputted by the Login endpoint
- A Project token from the Project/Create endpoint
- The profileToken(s) from the profile you wish to query
- The data type Id(s) you wish to query.

The code below provides an example of such a query using Python's `http.client` package. Note that the projectToken is required by the profileTokens and dataTypes can be empty. In such a case, all the profiles and / or all the data types will be returned by the query. Both the profileTokens and data type Ids are expected to coma delimited strings with the desired values.

A list of the different data types Ids and their corresponding channels is available in [Appendix A](#)

```
import http.client

token = "eyJhbGciOiJIUzI1BgLSnPnT5aCI5IstDGFK8.eyJzbX8GW86iJaaXNzb3VfQWlyZHJvcCI5InB0IjoiMmQ5ODE2YmY0OTkxNDUxOWEyMzE3M2E0ZjlmYmRhODciLCJleHAiOiJlE2NTk3MTU3MTMslmlzcyI6Imh0dHA6Ly9yb2NrbGFuZGFwaS5henVyZXdlYnNpB07EQ0G2B1XVTWxnaweb7Ctc8lnF1ZCI6ImFhNTQyZmZjLWU4NjltNDEwNy05NzY4YmlwN2M5YiJ9bFwE7QATquWW14ID7MA35iPhp2a5sSfozeLfMHyR4-I"

projectToken = "f8b45014-1606-4fbe-94f7-bdd9b24c802e"
profileTokens = "e96ccfc0,3e251bc3";
dataTypelds = "0xA11,0xA12,0x841,0x842"

conn = http.client.HTTPSConnection("localhost", 5001)
payload = ''
headers = {
    'Authorization': 'Bearer ' + token,
    'Cookie': 'allow-cookies=true'
}
conn.request("GET", "/api/Data/Get?projectToken="+ projectToken
    + "&profileTokens="+profileTokens
    + "&DataTpelds="+ dataTypelds, payload, headers)

res = conn.getresponse()
```

If successful the response body will contains an array of structures, one structure per profile in the project.

Each structure will contain the token of the profile, a data array for each subtype of the given data type, a time array, pressure array, and an array of data type ids corresponding to the subtypes of the data arrays:

```
"message": "",
"body": [
  {
    # First profile in the project
    [
      "profileToken": "e96ccfc0",
      "data": [
        [
          # data array of type 0xA11 (2577)

          3.394e-10,
          ...,
          2.983e-9
        ],
        [
          # data array of type 0xA12 (2578)

          4.584e-11,
          ...,
          3.689e-10
        ],
        [
          # data array of type 0x841 (2113)

          1.12,
          ...,
          2.56
        ],
        [
          # data array of type 0x842 (2114)

          0.56,
          ...,
          1.56
        ]
      ],
      "profileToken": "3e251bc3",
      "data": [# same structure as above]
    ]
    "typeIds": [
      2577,
      2578,
```

```
    2113,  
    2114  
  ]  
}  
]
```



The API endpoint has the capability to return spectral data as well. In those instances, the data array will be three (3) dimensional including a dimension for the spectra.

## A Data Types

The following table shows the different data types and their corresponding codes:

### Kinematics Sensor and Data:

Name	Code
Time	0x100
Accelerometer	0x110 (Ax +1, Ay +2, Az +3)
Piezo	0x120 (Ax +1, Ay +2)
Inclinometer	0x130 (X +1, Y +2, T +3)
Theta	0x140
Magnetometer	0x150 (Mx +1, My +2, Mz +3)
Pressure	0x160 (P +1)

**Table 1:** List of data types and their corresponding ids for kinematics sensor and data

### Instrument Meta Data:

Name	Code
Battery voltage	0x210
Pressure Voltage	0x220
EM Current	0x230
Position	0x240 (Lat +1, long +2, Z +3)

**Table 2:** List of data types and their corresponding ids for instrument meta data

### Instrument Speed:

Name	Code
EM	0x310
Vector	0x320
FallRate	0x330
Glide	0x340
HotelSpeed	0x350
Speed	0x360

**Table 3:** List of data types and their corresponding ids for instrument speed

**CT Sensor Data:**

Name	Code
Temperature	0x410 (Jac +1, SeaBird +2, RBR +3)
Conductivity	0x420 (Jac +1, SeaBird +2, RBR +3)
Salinity	0x430
Density	0x440
Viscosity	0x450

**Table 4:** List of data types and their corresponding ids for CT sensor data**Chlorophyll, turbidity and dissolved oxygen sensors:**

Name	Code
Chlorophyll	0x510
Turbidity	0x520
Dissolved Oxygen	0x530

**Table 5:** List of data types and their corresponding ids for chlorophyll, turbidity and dissolved oxygen sensors**Microstructure sensors:**

Name	Code
Shear	0x610 (sh1...sh15 → +1...0xF)
Therm	0x620 (T1...T15 → +1...0xF)
Ucond	0x630 (C1...C15 → +1...0xF)
Grad T	0x640 ( $\nabla T1... \nabla T15 \rightarrow +1...0xF$ )
Grad C	0x650 ( $\nabla C1... \nabla C15 \rightarrow +1...0xF$ )

**Table 6:** List of data types and their corresponding ids for microstructure sensors**Shear Quality Control:**

Name	Code
Kmax	0x810 (kmax_u1...kmax_u15 → +1...0xF)
Variance Resolved	0x820 (var_u1...var_u15 → +1...0xF)
MAD	0x830 ( $\mathcal{E}1 \text{ MAD}... \mathcal{E}15 \text{ MAD} \rightarrow +1...0xF$ )
Figure of Merit	0x840 ( $\mathcal{E}1 \text{ FoM}... \mathcal{E}15 \text{ FoM} \rightarrow +1...0xF$ )

**Table 7:** List of data types and their corresponding ids for shear quality control**Spectral Data:**

Name	Code
Frequency	0x910
Shear Spectra	0x920 (sh1 ... sh15 → +1...0x0F)
Cleaned Shear Spectra	0x930 (sh1 ... sh15 → +1...0x0F)
Temperature Spectra	0x940 (T1 ... T15 → +1...0x0F)
Cleaned Temperature Spectra	0x950 (T1 ... T15 → +1...0x0F)
Conductivity Spectra	0x960 (C1 ... C15 → +1...0x0F)
Cleaned Conductivity Spectra	0x970 (C1 ... C15 → +1...0x0F)
Vibration Spectra	0x980

**Table 8:** List of data types and their corresponding ids for spectral data

### Computed Values:

Name	Code
Dissipation	0xA10 ( $\varepsilon_1 \dots \varepsilon_{15} \rightarrow +1 \dots 0xF$ )
Buoyancy Frequency	0xA20
Eddy diffusivity	0xA30

**Table 9:** List of data types and their corresponding ids for computed values

End of document